

IMPORTANT - PLEASE READ!

QUICK START INSTRUCTIONS

SETTING MONITOR RESOLUTION

For RangeMaster Pro to display properly, you will need to set your monitor resolution to 800 x 600 or greater. To do this, click the Start button, point to Settings, click Control Panel, double click Display, click the Settings tab, and set the Screen Area to 800 x 600 or greater.

INSTALLATION INSTRUCTIONS

1. Click on step 2 "Download RangeMaster Pro now" from the <http://cornerstoneapplications.com/ver1/downloadrequest.html> form.
2. Click "Save this program to disk" from the File Download window. Then click Ok.
3. In the "Save As" window, indicate where you would like to save the "demo.exe" file. Then click Save.
4. Click Open in the "Download Complete" window.
5. Click Setup from the "Winzip Self-Extract" window.
6. Click Continue from the RangeMaster Pro Setup window.
7. Click Ok when asked if you want to install RangeMaster Pro in the C:\Range directory.
8. Click Typical
9. Click Ok when it tells you "RangeMaster Pro Setup was completed successfully."

INITIAL DATA ENTRY INSTRUCTIONS

1. Open RangeMaster Pro by clicking the Start button, Programs, RangeMaster Pro, RangeMaster Pro. You will be asked to enter a user name and password. Enter the user name "Update". No passwords have been created so leave the password blank. (There is a second user name that can be used later, for users who do not have the authority to change data, but do want to view the data. That user name is "View". There is no password associated with this user name either. If you sign on with user name of Update, you will be able to add, delete and change data. If you sign on with View, you will not be able to perform any adds, changes or deletes. You will only be allowed to view information and reports.)
2. Once RangeMaster Pro is running, enter the officer information for instructors and armorers. (Do not enter their firearm, qualification, maintenance, equipment or officer supplemental information at this time.) Click on the "How Do I?" button in the upper right corner of the window. This will display a list of simple, easy to read instructions for entering new data.
3. Click on the Table Maintenance button in the upper right corner of the RangeMaster Pro window to access the lookup tables. Enter data in all the lookup tables, being sure to identify instructors and armorers in the Instructor Table.

Note! If you use the pass/fail method of scoring qualifications instead of tracking individual scores, the following is the simplest way to accomplish this. When you define a course, specify a passing score of 1. Then when you enter a qualification, enter a target score of 1 for pass and 0 for fail.
4. Close the Table Maintenance window and enter remaining officer, firearm, qualification, maintenance, equipment/holster and supplemental information.

IF YOU EXPERIENCE PROBLEMS RUNNING RANGEMASTER PRO HELP

RangeMaster Pro uses the latest Microsoft Help software that requires Internet Explorer 3.5 or greater. If you experience any problems running RangeMaster Pro Help please install the Microsoft Internet Explorer by clicking on the Microsoft link on the download form.